

Data Exploration User Manual

Created By: Oak Ridge National Laboratory


Last Updated: 3/9/2022

Table of Contents

Module Navigation.....	3
Main Tabs.....	3
Additional Buttons	3
Setup	4
Navigation	4
Setup Data.....	5
Day Type Analysis.....	7
Run Analysis	7
Managing Day Types	7
Day Type Exploration	8
Visualization	9
Modify Chart	9
Annotations.....	10
Data Summary and Help	10

Module Navigation

Use the top banner to navigate around the module. A footer bar with “Next” and “Back” button can also be used to move through the Setup to the Day Type Analysis.



Main Tabs

Setup – Upload and format the data to be used.

Day Type Analysis – Conduct analysis on time interval data to determine day types.

Visualization – Create and customize a variety of graph types based on your uploaded data.

*Some of the tabs will be disabled until the Setup is completed.

Additional Buttons

Download – Download a .json file of the current state of your data exploration module. Files can be uploaded later in setup to restore the current state.

Book – The book will open a new window with the Compressed Air User Manual you are reading.


Home – The house will bring you to MEASUR’s home page.

Setup

The setup is where you upload and select the data to include in the Data Exploration.

Navigation

Use the second bar to navigate to different sections of the Setup. The tabs will be color coded to indicate the state of the corresponding tab data. Tabs will be disabled if the previous steps have errors in their data.



Setup Data – Upload data files

Clean Data – Tell the explorer more about the data you are using.

Tab colors:

Green - Valid data entered for tab.

Red – Invalid or missing data entered for tab.

Gray – Disabled tab, previous tabs are incomplete.

Setup Data

The data explorer will take in .csv, .xlsx, or .json data files. Only .json files previously exported from the Data Explorer are permitted. It should be noted that larger data files may take longer to parse and analyze.

1 Setup Data

2 Clean Data

IMPORT LOGGER DATA

Start Over

Log File

Choose File

Sample compressed air data.xlsx

Choose Worksheet

5 Second

Select Header Row

<input checked="" type="radio"/> Time	Comp1Amps	Comp2Amps	Comp3Amps	Comp4Amps	Pressure 1	Pressure 2	Pressure 3	Pressure 4
<input type="radio"/> 09/23/2019 05:00:00	208.08	354.83	457.825	501.45	83.503	76.944	76.944	81.927
<input type="radio"/> 09/23/2019 05:00:05	211.99	354.045	447.735	511.41	82.431	76.439	76.439	82.368
<input type="radio"/> 09/23/2019 05:00:10	211.46	352.095	458.15	519.415	82.305	76.313	76.313	82.179
<input type="radio"/> 09/23/2019 05:00:15	217.58	354.96	471.5	510.04	82.116	76.187	76.187	82.053
<input type="radio"/> 09/23/2019 05:00:20	214.33	368.175	461.93	505.355	82.053	76.187	76.187	81.99
<input type="radio"/> 09/23/2019 05:00:25	215.24	363.16	479.44	513.69	81.927	76.187	76.187	81.927
<input type="radio"/> 09/23/2019 05:00:30	211.99	360.1	468.44	533.545	82.116	76.124	76.124	82.053
<input type="radio"/> 09/23/2019 05:00:35	217.98	366.415	461.145	517.075	82.242	76.124	76.124	82.179
<input type="radio"/> 09/23/2019 05:00:40	210.68	357.305	466.615	516.16	82.557	76.124	76.124	82.368
<input type="radio"/> 09/23/2019 05:00:45	218.5	365.18	463.165	517.14	82.431	76.187	76.187	82.368

Parse CSV Data

First choose the file you wish to upload. Depending on the file type there may be additional steps. For .xlsx files you will have to choose the worksheet that the data you wish to use is in and the header row for the data table. A preview of the worksheet table is provided.

Once the worksheet and header row are selected click the “Parse CSV Data” button and the explorer will parse the data.

If you make a mistake at any time during this process you can click “Start Over” to clear out your data and start again.

Clean Data

Once data has been setup, the next step will be to clean the data.

1 Setup Data

2 Clean Data

DATA SUMMARY

Data Columns (Sample compressed air data.xlsx)					
Use Column	Is Date	Is Time	Column Name	Alias	Unit
<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Time	Time	
<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	Comp1Amps	Current 1	A
<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	Comp2Amps	Current 2	A
<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	Comp3Amps	Comp3Amps	+Add
<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	Comp4Amps	Comp4Amps	+Add
<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	Pressure 1	Pressure 1	psig
<input checked="" type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	Pressure 2	Pressure 2	psig
<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	Pressure 3	Pressure 3	+Add
<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	Pressure 4	Pressure 4	+Add

Submit

To clean your data for exploration:

- Select the columns you wish to include
- Identify which column is a date or time (a date or time column is necessary for Day Type Analysis)
- Provide an "Alias" or label you wish this data column to have throughout the explorer.
- Add a "Unit" label that will be applied to the data in the explorer.

Once your data has been "cleaned", click on the "Submit" button and you will be ready to continue to "Day Type Analysis" or "Data Visualization".


Day Type Analysis

The “Day Type Analysis” section provides the ability to break your data down into “Day Types” or similar days of system operation. **A date or time field is required in your data for analysis.**

Run Analysis


To start you will have to click the “Run Analysis” button. This will organize your data into days and then determine if those days are in one of three categories:

- Weekend
- Weekday
- Excluded (not a full days worth of readings)



Managing Day Types

As stated above, initial analysis will separate your days into three default day types. The days and their corresponding day types will be displayed in the calender at the bottom of the “Day Type Analysis” screen.




Use this calender to manage your day types and their corresponding days by:

- Clicking the dates to toggle the day type of that date.
- Removing day types completely by clicking the day type labels at the top.
- Creating additional day types with the “+Add New” link in the upper right.

Day Type Exploration

The data and day types can be explored in a variety of ways using the menu at the top to:

- View the data graphically or as a data table (top left)
- Toggle between viewing days or day types (top right)
- Select the data column using the dropdown (top right)




*Note if using compressed air data: Once day type analysis is completed and you are happy with the day types, you can click the “Apply To Assessment” button in the upper right hand corner. This will allow you to apply the day types to an existing compressed air assessment or start a new assessment with the day type data.

Visualization

Use the “Visualization” tab to generate scatter plots and histograms of your data.

*Note: This feature is a work in progress and can currently run slow with lots of data in the system.



Modify Chart

Use the menu on the left hand side of the screen to customize the chart.

The image shows the configuration menu for the "Compressor Time Series" chart. The menu is organized into sections: "Graph Basics", "X Axis", and "Y Axis".
- In "Graph Basics", the chart type is set to "Scatter Plot" and markers are visible.
- In "X Axis", the axis label is "X Axis Label" and the data type is "Time Series".
- In "Y Axis", there are two data series:
 - "Comp1Amps": Data source is "Comp1Amps", series color is green.
 - "Comp2Amps": Data source is "Comp2Amps", series color is blue.
 Each series has a "Remove Data Series" button. A "+Add Axis" button is at the bottom.

Choose the type of plot you want between “Scatter” and “Histogram”.

If “Histogram” is selected then some options for binning will appear.

Choose the data you want represented by the X Axis. The last option in the dropdown will be “Time Series”.

Multiple data variables can be added to the Y Axis. You can select the data and its corresponding color on the graph.

A second Y Axis can be added and will be placed on the right hand side of the chart with the “+Add Axis”

Annotations

You can annotate the chart by clicking on a data point. Once a data point is selected the “Annotations” section on the left hand menu will look like this:

The screenshot shows the 'Annotations' panel on the left side of a software interface. It has a title bar with a dropdown arrow and the text 'Annotations'. Below the title bar, there are several fields: 'Selected Series' with the value 'Comp2Amps', 'Selected X Point' with the value '2019-09-26 04:48:30', and 'Selected Y Point' with the value '408.28'. Below these is a text box labeled 'Annotation' with a small diagonal icon in the bottom right corner. Under the text box are five settings: 'Font Size' with a dropdown menu showing '16', 'Font Color' with a black color swatch, 'Background Color' with a white color swatch, 'Arrow Color' with a black color swatch, and 'Arrow Size' with a dropdown menu showing '1'. At the bottom of the panel are four arrow buttons: left, up, down, and right. Below the buttons is a yellow button with the text 'Click on a data point to annotate.'

Whatever you add to the text box will be added to the chart. Use the options to customize the size and color of the annotation. Use the arrow buttons to move the annotation.

A list of current annotations will appear underneath this window.

If you leave the Visualization screen or change the data on the graph then the annotations will be removed.

Data Summary and Help

A summary of the data in the chart is provided in a table at the bottom of the page. Additionally, some help text with further information can be found underneath the “Help” tab here.

DATA SUMMARY		HELP	
Time Data		Data Summary	
CSV	Sample compressed air data-reduced.csv	Axis	Y-Axis
Start Time	Sep 23, 2019, 5:00:00 AM	Data Field	Comp1Amps
End Time	Oct 2, 2019, 11:53:00 PM	Max	1,214.88
Data Frequency	5 seconds	Min	156.52
		Mean	238.88
		Std. Deviation	71.56
		# of Samples	169128